

LEGO Engineering

Using RoboLab with Control Lab 9751 (Interface B)

You may be experiencing problems if you are not using the specific Control Lab Interface icons.

To use Control Lab with RoboLab, go to Inventor 4 in RoboLab. From the functions palette, select Control Lab Interface. This new palette displays all of the controls that can be used with RoboLab and Control Lab. It is very important that you replace the Begin icon in Investigator (green traffic light) with the Begin Control Lab icon in the Control Lab Interface Palette.

Also, be sure to wire the number of the port on the machine that Control Lab is connected to to the port number in the upper left of the Begin Control Lab icon. For more information on this, select Show Context Help from the menu and then move your cursor over the Begin Control Lab icon.

<http://www.legoengineering.com/knowledgemanager/questions/32/>